

Setting Up CANalyst-ii

1. Make sure you have Windows 10 64 bit and have python installed
2. Download and Install [ZagDig](#)
3. Connect CANalyst-ii to the computer
4. Unplug any other devices
5. Open ZagDig
6. To the right of the green arrow select *libusb-win32*
7. Click *Install WCID Driver*
8. You can close ZagDig
9. Open Command Prompt
10. Run 'py -m install pip pyusb'
11. In case you need to update pip 'py -m pip install --upgrade pip'
12. Run 'py -m pip install "python-can[canalystii]"
13. Download [Visual Studio Code](#)
14. Install Python Extension